

Scientific Data Sets (DFSD API)

11.1 Chapter Overview


The DFSD interface is one of two interfaces in the HDF library that support the scientific data model. With the release of HDF version 3.3, the multifile SD interface described in Chapter 3, titled *Scientific Data Sets (SD API)*, was made available. Generally, the SD interface should be used instead of the DFSD interface.

11.2 The DFSD Scientific Data Set Data Model

The scientific data set, or SDS, data model supports four primary data objects: arrays, dimensions, dimension scales, and dimension attributes. As in the multifile SD SDS model, the fundamental object of the data model is the SDS array. Unlike the SD multifile SDS model the DFSD SDS model has, in addition to dimension attributes, attributes that refer to the SDS array itself.

FIGURE 11a

The Contents of a Three-Dimensional DFSD Scientific Data Set



11.2.1 Required DFSD SDS Objects

The only required objects in the DFSD SDS model are the **array** and the **number type** of the array data. Without this information, the data set is inaccessible. Required objects are created by the library using the information supplied at the time the SDS is defined.

Descriptions of these objects in Chapter 3, titled *Scientific Data Sets (SD API)*.

11.2.1.1 Dimensions

Unlimited dimensions, supported in the multifile SD SDS model, aren't supported in the single-file DFSD SDS model.

11.2.2 Optional DFSD SDS Objects

There are two types of optional objects available for inclusion in an SDS: dimension scales and attributes. Optional objects are only created when specified by the calling program.

11.2.2.1 Dimension Scales

Conceptually, *adimension scale* is a series of numbers placed along a dimension to demarcate intervals in a data set. They are assigned one per dimension. Structurally, each dimension scale is a one-dimensional array with size and name equal to its assigned dimension name and size.

11.2.2.2 Predefined Attributes

Predefined attributes are attributes that have reserved labels and in some cases predefined number types. They are described in Chapter 3, titled *Scientific Data Sets (SD API)*.

11.3 The Single-File Scientific Data Set Interface

The HDF library currently contains several routines for storing scientific data sets in the HDF format. **DFSDadddata**, **DFSDputdata**, and **DFSDgetdata** perform data I/O and by default assume that all scientific data is uncompressed 32-bit floating-point data stored in row-major order. DFSD library routines also read and write subsets and slabs of data, set defaults, determine the number of data sets in a file, and inquire about or assigning reference numbers before reading or writing data.

11.3.1 DFSD Library Routines

The names of the C routines in the DFSD library are prefaced by "DFSD" and the names of the equivalent Fortran-77 functions are prefaced by "ds". They are categorized as follows:

- *Write routines* create new data sets and add slabs to existing data sets.
- *Read routines* read whole scientific data sets.
- *Slab routines* read and write subsets and slabs of scientific data.
- *Data set attribute routines* read and write the predefined string and value attributes assigned to data sets.
- *Dimension attribute routines* read and write the predefined string and value attributes assigned to dimensions.

DFSD library routines are more explicitly defined in Table 11A and on their respective pages in the *HDF Reference Guide*.

TABLE 11A

DFSD Library Routines

Category	Routine Name		Description
	C	Fortran-77	
Write	DFSDadddata	dsadata	Appends a data set to a file.
	DFSDclear	dsclear	Clears all possible set values.
	DFSDputdata	dspdata	Overwrites new data to a file.
	DFSDsetdims	dssdims	Sets the rank and dimension for succeeding data sets.
	DFSDsetNT	dsnt	Sets the number type for the data set.
	DFSDwriteref	dswref	Assigns a reference number to the next data set written.
Read	DFSDgetdata	dsgdata	Retrieves the next data set in the file.
	DFSDgetdims	dsgdims	Returns the number and dimensions for the next data set.
	DFSDgetNT	dsgnt	Determines the number type for the data in the data set.
	DFSDlastref	dslref	Returns the reference number of last data set accessed.
	DFSDndatasets	dsnum	Returns the number of data sets in a file.
	DFSDpre32sdg	dsp32sd	Determines if the data set was created before HDF version 3.2.
	DFSDreadref	dsrref	Locates a data set with the specified reference number.
	DFSDrestart	dsfirst	Sets the location of the next access operation to be the first data set in the file.
Slabs	DFSDendslab	dssslab	Terminates a read or write slab operation.
	DFSDreadslab	dsrslab	Reads a slab of data from a data set.
	DFSDstartslab	dssslab	Begins a read or write slab operation.
	DFSDwriteslab	dswnslab	Writes a slab of data to a data set.
Data Set Attribute	DFSDgetcal	dsgcal	Retrieves the calibration information for the data set.
	DFSDgetdatalen	dsgdln	Retrieves the length of the attributes assigned to the data.
	DFSDgetdatastrs	dsgdast	Returns the label, unit, format and coordinate system for data.
	DFSDgetfillvalue	dsgfill	Retrieves the fill value used to complete the data set.
	DFSDgetrange	dsgrang	Retrieves the range of values for the data set.
	DFSDsetcal	dsscal	Sets the calibration information for the data set.
	DFSDsetdatastrs	dssdast	Sets label, unit, format and coordinate system for data.
	DFSDsetfillvalue	dssfill	Sets the fill value to use when completing a data set.
	DFSDsetlengths	dsslens	Sets the length for the data set and dimension attributes.
Dimension Attribute	DFSDsetrange	dssrang	Sets the range of values for the data set.
	DFSDgetdimlen	dsgdiLn	Retrieves the length of the attributes assigned to the dimension.
	DFSDgetdimscale	dsgdisc	Returns the scale for a dimension.
	DFSDgetdimstrs	dsgdist	Returns the label, unit, and format for a dimension.
	DFSDsetdimscale	dssdisc	Sets the scale for a dimension.
	DFSDsetdimstrs	dssdist	Sets the label, unit and format for the dimension.

11.3.2 File Identifiers in the DFSD Interface

File identifiers are handled internally by each routine and access to a file is granted simply by providing a filename. As the file identifier is handled by the function call, the calling program need not keep track of how to open and close files.

11.4 Writing DFSD Scientific Data Sets

The DFSD programming model for writing an SDS to an HDF file involves the following steps:

1. Define data set options. (optional)

2. Write all or part of the data set.

These steps are performed for every data set written to a file. However, it is not always necessary to define data set options for every write operation as setting an option places information about the data set in a structure in primary memory. This information is retained until explicitly altered by another set call.

11.4.1 Creating a DFSD Scientific Data Set: DFSDadddata and DFSDputdata

To define and write a single SDS, the calling program must contain of of the following routines:

```
C:                status = DFSDadddata(filename, rank, dim_sizes, data);
FORTRAN:          status = dsadata(filename, rank, dim_sizes, data)
```

or

```
C:                status = DFSDputdata(filename, rank, dim_sizes, data);
FORTRAN:          status = dspdata(filename, rank, dim_sizes, data)
```

DFSDadddata appends data to a file when given an existing file name and creates a new file when given a unique file name. **DFSDputdata** replaces the contents of a file when given an existing file name and creates a new file when given a unique file name. To avoid accidentally overwriting data in a file, the use of **DFSDadddata** is recommended.

DFSDadddata and **DFSDputdata** have four parameters: `filename`, `rank`, `dim_sizes`, and `data`. In both routines, the data set is written to the file specified by the `filename` parameter. The total number of dimensions in the array and the size of each dimension are passed in the `rank` and `dim_sizes` parameters. A pointer to the data or slab of data written to the named file is passed in the `data` parameter.

The parameters of **DFSDadddata** and **DFSDputdata** are further described in the following table.

TABLE 11B

DFSDadddata and DFSDputdata Parameter List.

Routine Name (Fortran-77)	Parameter	Data Type		Description
		C	Fortran-77	
DFSDadddata (dsadata)	filename	char *	character* (*)	Name of the file containing the data set.
	rank	int32	integer	Number of dimensions in the array.
	dim_sizes	int32 *	integer (*)	Size of each dimension in the data array.
	data	VOIDP	<valid numeric data type>	Array containing the data.
DFSDputdata (dsadata)	filename	char *	character* (*)	Name of file containing the data set.
	rank	int32	integer	Number of dimensions in the array.
	dim_sizes	int32 *	integer (*)	Size of each dimension in the data array.
	data	VOIDP	<valid numeric data type>	Array containing the data.

11.4.2 Specifying the Data Type of a DFSD SDS: DFSDsetNT

The default data type for scientific data is `DFNT_FLOAT32`. To change the default setting, the calling program must contain calls to the following routines:

```
C:                status = DFSDsetNT(number_type);
                  status = DFSDadddata(filename, rank, dim_sizes, data);
```

```

FORTRAN:      status = dssnt(number_type)
              status = dsadata(filename, rank, dim_sizes, data)

```

DFSDsetNT defines the data type for all subsequent **DFSDadddata** and **DFSDputdata** calls until it is changed by a subsequent call to **DFSDsetNT** or reset to the default by **DFSDclear**. **DFSDsetNT**'s only parameter is the data type.

EXAMPLE 1.

Creating and Writing to a DFSD Scientific Data Set

In the following code examples, **DFSDadddata** is used to write an array of 64-bit floating-point numbers to a file named "Example1.hdf". Although the **DFSDsetNT** function call is optional, it is included here to demonstrate how to override the `float32` default.

```

C:  #include "hdf.h"

    #define LENGTH 3
    #define HEIGHT 2
    #define WIDTH 5

    main( )
    {

        /* Create data array - store dimensions in array 'dims' */
        static float64 scien_data[LENGTH][HEIGHT][WIDTH] =
            { 1., 2., 3., 4., 5.,
              6., 7., 8., 9.,10.,
              11.,12.,13.,14.,15.,
              16.,17.,18.,19.,20.,
              21.,22.,23.,24.,25.,
              26.,27.,28.,29.,30. };
        int32 dims[3] = {LENGTH, HEIGHT, WIDTH};
        intn status;

        /* Set number type to 64-bit float */
        status = DFSDsetNT(DFNT_FLOAT64);

        /* Write the data to file */
        status = DFSDadddata("Example1.hdf", 3, dims, scien_data);

    }

```

```

FORTRAN:      PROGRAM WRITE SDS

              integer dsadata, dssnt, dims(3), status
              real*8   sci_data(5,2,3)

C             Create array called 'sci_data'; store dimensions in array 'dims'.
data         sci_data/ 1., 2., 3., 4., 5.,
$              6., 7., 8., 9.,10.,
$              11.,12.,13.,14.,15.,
$              16.,17.,18.,19.,20.,
$              21.,22.,23.,24.,25.,
$              26.,27.,28.,29.,30./

              data dims /3,2,5/

C             Set number type to 64-bit float
              status = dssnt(6)

C             Write the data to file

```

```
status = dsadata('Example1.hdf', 3, dims, sci_data)

stop
end
```

11.4.3 Overwriting Data for a Given Reference Number: DFSDwriteref

DFSDwriteref is a highly specialized function call that overwrites data referred to by the specified reference number.

If DFSDwriteref is called with a reference number that doesn't exist, an error return value of -1 will be returned.

The following series of function calls should appear in your program:

```
C:          status = DFSDwriteref(filename, ref_number);
           status = DFSDadddata(filename, rank, dim_sizes, data);

FORTRAN:    status = dswref(filename, ref_number)
           status = dsadata(filename, rank, dim_sizes, data)
```

If the filename passed to DFSDwriteref is different from the filename in the DFSDadddata or DFSDputdata routine calls, it will be ignored. The next scientific data set written, regardless of the filename, is assigned the reference number ref_number.

Care should be taken when using DFSDwriteref, as once the new data has been written the old data cannot be retrieved.

The parameters of DFSDwriteref are described in the following table.

TABLE 11C

DFSDsetNT and DFSDwriteref Parameter List

Routine Name (Fortran-77)	Parameter	Data Type		Description
		C	Fortran-77	
DFSDsetNT (dssNT)	number_type	int32	integer	Number type tag.
DFSDwriteref (dswref)	filename	char *	character* (*)	Name of the file containing the data.
	ref_number	int16	integer	Reference number to be assigned to the data setcreated.

11.4.4 Writing Several Data Sets: DFSDsetdims and DFSDclear

The DFSD programming model for writing multiple data sets to an HDF file is identical to that for writing individual data sets. (Refer to Section 11.4 on page 275). To understand how multiple data sets are written to file, it is first necessary to take a closer look at each step of the programming model. First and most importantly, all DFSD routines that set a write option except DFSDsetNT and DFSDsetfillvalue add information to a special structure in primary memory. This information is used to determine how data is written to file for all subsequent write operations.

Information stored in primary memory is retained by the HDF library until explicitly changed by a call to DFSDsetdims or reset to NULL by calling DFSDclear. DFSDsetdims and DFSDclear are used to prevent assignments of attributes created for a group of data sets to data sets outside the group. For more information on assigning attributes see Section 11.7.1 on page 286 and Section 11.7.3 on page 293.

11.4.5 Preventing the Reassignment of DFSD Data Set Attributes: DFSDsetdims

Information stored in primary memory is retained by the HDF library until explicitly changed by a call to **DFSDsetdims** or reset to NULL by calling **DFSDclear**. **DFSDsetdims** and **DFSDclear** are used to prevent assignments of attributes created for a group of data sets to data sets outside the group.

The syntax of **DFSDsetdims** is the following:

```
C:                status = DFSDsetdims(rank, dim_sizes);
FORTRAN:          status = dssdims(rank, dim_sizes)
```

DFSDsetdims is not used here to define the rank and dimension sizes to be used in the next operation, but to alert the DFSD interface to stop the automatic assignment of attributes to the data sets to be written to file. **DFSDsetdims** has two parameters: `rank` and `dim_sizes`. The rank of an array is the total number of dimensions in the array and the dimension sizes are the length of each individual dimension.

As a rule of thumb, **DFSDsetdims** should be called if any **DFSDset*** routine (**DFSDsetNT**, for example) has been called. This insures that all attribute values that have been reset will be assigned in future data set operations.

The parameters of **DFSDsetdims** are further defined in the following table.

TABLE 11D

DFSDsetdims Parameter List

Routine Name (Fortran-77)	Parameter	Data Type		Description
		C	Fortran-77	
DFSDsetdims (dssdims)	<code>rank</code>	<code>intn</code>	<code>integer</code>	Number of dimensions in the array.
	<code>dim_sizes</code>	<code>int32*</code>	<code>integer (*)</code>	Size of each dimension in the array.

11.4.6 Resetting the Default DFSD Interface Settings: DFSDclear

The syntax for **DFSDclear** is as follows:

```
C:                status = DFSDclear( );
FORTRAN:          status = dsclear( )
```

The **DFSDclear** routine clears all interface settings defined by any of the **DFSDset** routines (**DFSDsetNT**, **DFSDsetfillvalue**, **DFSDsetdims**, **DFSDsetdatastrs**, **DFSDsetdatalengths**, **DFSDsetrange**, **DFSDsetcal**, **DFSDsetdimsscale** and **DFSDsetdimstrs**). After the **DFSDclear** has been called, calls to any of the **DFSDset** routines will result in the corresponding value not being written. To write new values, call the appropriate **DFSDset** routine again.

TABLE 11E

DFSDclear Parameter List

Routine Name (Fortran-77)	Parameter	Data Type		Description
		C	Fortran-77	
DFSDclear (dsclear)	<code>None</code>	<code>None</code>	<code>None</code>	Clears all DFSD interface settings.

11.5 Reading DFSD Scientific Data Sets

The DFSD programming model for reading an SDS is also a two-step operation:

1. Obtain information about the data set if necessary.
2. Read all or part of the data set.

These steps are performed for every data set read. In some cases, calls to determine the data set definition may be reduced or avoided completely. For example, if the data set dimensions are known, the call that returns the data set dimensions may be eliminated.

11.5.1 Reading a DFSD SDS: DFSDgetdata

If the dimensions of the data set are known, **DFSDgetdata** is the only function call required to read an SDS. If the file is being opened for the first time, **DFSDgetdata** returns the first data set in the file. Any subsequent calls will return successive data sets in the file - data sets are read in the same order they were written. Normally, **DFSDgetdims** is called before **DFSDgetdata** so that space allocations for the array can be checked if necessary and the dimensions verified. If this information is already known, **DFSDgetdims** may be omitted.

To read an SDS of known dimension and number type, the calling program should include the following routine:

```
C:                status = DFSDgetdata(filename, rank, dim_sizes, data);

FORTRAN:          status = dsldata(filename, rank, dim_sizes, data)
```

DFSDgetdata has four parameters: `filename`, `rank`, `dim_sizes`, and `data`. **DFSDgetdata** returns a data set specified by the parameter `filename`. The total number of dimensions is specified in `rank` and the size of each dimension is specified in `dim_sizes`. **DFSDgetdata** returns the array in `data`.

The parameters of **DFSDgetdata** are further defined in the following table.

TABLE 11F

DFSDgetdata Parameter List

Routine Name (Fortran-77)	Parameter	Data Type		Description
		C	Fortran-77	
DFSDgetdata (<code>dsldata</code>)	<code>filename</code>	char	character* (*)	Name of the file containing the data.
	<code>rank</code>	int32	integer	Number of dimensions.
	<code>dim_sizes</code>	int32 *	integer (*)	Buffer for the dimension sizes.
	<code>data</code>	VOIDP	<valid numeric data type>	Buffer for the stored scientific dat.

11.5.2 Specifying the Dimensions and Data Type of an SDS: DFSDgetdims and DFSDgetNT

When **DFSDgetdims** is first called, it returns dimension information of the first data set. Subsequent calls will return this information for successive data sets. If you need to determine the dimensions or the data type of an array before reading it, call **DFSDgetdims** and **DFSDgetNT**. **DFSDgetNT** gets the data type (or, in HDF parlance, number type) of the data retrieved in the next read operation.

To determine the dimensions and data type of an array before attempting to read it, the calling program must include the following:


```

C:          status = DFSDgetdims(filename, rank, dimsizes, max_rank);
           status = DFSDgetNT(number_type);
           status = DFSDgetdata(filename, rank, dimsizes, data);

FORTRAN:    status = ds CNT(filename, rank, dimsizes, max_rank)
           status = ds gdims(number_type)
           status = ds gdata(filename, rank, dimsizes, data)

```

DFSDgetdims has four parameters: `filename`, `rank`, `dim_sizes`, and `maxrank`. The number of dimensions is returned in `rank`, the size of each dimension in the array `dim_sizes`, and the size of the array containing the dimensions sizes in `max_rank`. **DFSDgetNT** has only one parameter: `number_type`. As there is no way to specify the file or data set through the use of **DFSDgetNT**, it is only valid if it is called after **DFSDgetdims**.

The parameters of **DFSDgetdims** and **DFSDgetNT** are further defined in the following table.

TABLE 11G

DFSDgetNT and DFSDgetdims Parameter List

Routine Name (Fortran-77)	Parameter	Data Type		Description
		C	Fortran-77	
DFSDgetdims (ds gdims)	filename	char *	character* (*)	Name of file containing the data.
	rank	intn *	integer	Number of dimensions.
	dim_sizes	int32 *	integer	Buffer for the dimension sizes.
	max_rank	intn	integer	Size of the dimension size buffer.
DFSDgetNT (ds gnt)	number_type	int32 *	integer	Data type of the data to be read.

EXAMPLE 2.

Reading from a DFSD Scientific Data Set

The following examples search the file named "Example1.hdf" for the dimensions and data type of a DFSD array. Although use of **DFSDgetdims** and **DFSDgetNT** is optional, they are included here as a demonstration of how to verify the array dimensions and number type before reading any data. If the dimensions and type are known, only a call to **DFSDgetdata** is required.

```

C:  #include "hdf.h"

    #define LENGTH 3
    #define HEIGHT 2
    #define WIDTH 5

    main( )
    {

        float64 scien_data[LENGTH][HEIGHT][WIDTH];
        int32 number_type;
        intn rank, status;
        int32 dims[3];

        /* Get the dimensions and number type of the array */
        status = DFSDgetdims("Example1.hdf", &rank, dims, 3);
        status = DFSDgetNT(&number_type);

        /* Read the array if the dimensions are correct */
        if (dims[0] <= LENGTH && dims[1] <= HEIGHT && dims[2] <= WIDTH)
            status = DFSDgetdata("Example1.hdf", rank, dims, scien_data);

    }

```

```
FORTTRAN:      PROGRAM READ SDS

                  integer  dsldata, dsldims, dsldnt, dims(3), status
                  integer  rank, num_type
                  real*8    sci_data(5, 2, 3)

C               Get the dimensions and number type of the array.
                  status = dsldims('Example1.hdf', rank, dims, 3)
                  status = dsldnt(num_type)

C               Read the array if the dimensions are correct.
                  if ((dims(1) .eq. 3) .and. (dims(2) .eq. 2) .and.
+                   (dims(3) .eq. 5)) then
                      status = dsldata('Example1.hdf', rank, dims, sci_data)
                  endif

                  end
```

11.5.3 Determining the Number of DFSD Data Sets: DFSDndatasets and DFSDrestart

DFSDgetdims and **DFSDgetdata** sequentially access DFSD data sets. By repeatedly calling either function, a program can step through an entire file by reading one data set at a time. However, before attempting to sequentially access all of the data sets in a file the total number of data sets in the file should be determined. To do so, the calling program must call the following routine:

```
C:               num_of_datasets = DFSDndatasets(filename);

FORTTRAN:      num_of_datasets = dsnum(filename)
```

Once the total number of data sets is known, a calling program can at any time, reset the current data set to the first data set in the file by calling the following routine:

```
C:               status = DFSDrestart( );

FORTTRAN:      status = dsfirst( )
```

Use of **DFSDndatasets** and **DFSDrestart** is optional, it is usually more convenient than cycling through the entire file one SDS at a time.

11.5.4 Obtaining Reference Numbers of DFSD Data Sets: DFSDreadref and DFSDlastref

As the HDF library handles the assignment and tracking of reference numbers, reference numbers must be explicitly returned. Obtaining the reference number is an operation best performed immediately after data set creation.

The DFSD interface uses the function **DFSDreadref** to initiate access to individual scientific data sets. **DFSDreadref** specifies the reference number of the next SDS to be read.

To access a specific SDS, the calling program must contain the following routines:

```
C:               status = DFSDreadref(filename, ref);
                  status = DFSDgetdata(filename, rank, dim_sizes, data);

FORTTRAN:      status = dsrref(filename, ref)
```

```
status = dsdata(filename, rank, dim_sizes, data)
```

DFSDreadref has two parameters: `filename` and `ref`. **DFSDreadref** specifies the reference number of the object to be next operated on in the HDF file `filename` as `ref`. Determining the correct reference number is the most difficult part of this operation. As a result, **DFSDreadref** is often used in conjunction with **DFSDlastref**, which determines the reference number of the last data set accessed.

To syntax of **DFSDadddata** and **DFSDlastref** is:

```
C:          status = DFSDadddata(filename, rank, dim_sizes, data);
           ref_num = DFSDlastref( );

FORTRAN:    status = dsadata(filename, rank, dim_sizes, data)
           ref_num = dslref( )
```

DFSDputdata can also be used with **DFSDlastref** to obtain similar results. In any case, **DFSDlastref** can be used before any operation that requires identifying a scientific data set by reference number, as in the assignment of annotations and inserting data sets into vgroups. For more information about annotations and vgroups refer to Chapter 10, titled *Annotations (DFAN API)*, and Chapter 5, titled *Vgroups (V API)*.

TABLE 11H

DFSDreadref Parameter List

Routine Name (Fortran-77)	Parameter	Data Type		Description
		C	Fortran-77	
DFSDreadref (dsrref)	<code>filename</code>	char *	character* (*)	Name of the file containing the data set.
	<code>ref_number</code>	uint16	integer	Reference number of the next data set to be read.

11.6 Slabs in the DFSD Interface

To review, *aslab* is an n-dimensional array whose dimensions are smaller than those of the SDS array into which it is written or from which it is read.

11.6.1 Accessing Slabs: DFSDstartslab and DFSDendslab

There are two routines required for every DFSD slab operation - **DFSDstartslab** and **DFSDendslab**. **DFSDstartslab** is used to initialize the slab interface and to initiate access to new or existing data sets. **DFSDendslab** is used to terminate access to open data sets. **DFSDstartslab** must be called before any read or write slab operation and **DFSDendslab** must be called after the slab operation is completed. Both routines are required when reading and writing slabs.

Given a new filename, **DFSDstartslab** will create a new HDF file with the specified name. Given an existing filename, it will open the named file and append the new data set to the end of the file. Its only parameter is `filename`. **DFSDendslab** has no parameters and need only be called once per file. **DFSDendslab** will write any attributes defined immediately before the data set is created.

For more information on assigning attributes, see Section 11.7.3 on page 293.

TABLE 11I

DFSDstartslab Parameter List

Routine Name (Fortran-77)	Parameter	Data Type		Description
		C	Fortran-77	
DFSDstartslab (dssslab)	filename	char *	character* (*)	Name of the file containing the data set.

11.6.2 Writing Slabs: DFSDwriteslab

In the DFSD interface, writing an entire data set array and writing slabs follow the same programming model. The difference between the two is that calls to three routines is needed to write slabs, while a call to one routine is needed to write whole data sets.

More specifically, the DFSD programming model for writing slabs to an SDS is as follows:

1. Set the appropriate options to define the new SDS or select an existing SDS.
2. Write the data set using three specialized slab routines.

In addition to writing slabs to both new and existing data sets, **DFSDwriteslab** can also perform the following sequential write operations:

- Write slabs to a single data set when called repeatedly.
- Write slabs to sequential data sets when repeatedly called between calls to **DFSDgetdims**.
- Write slabs to selected data sets when repeatedly called between calls to **DFSDwriteref**.

Although not specifically defined as a slab routine, in practice, the **DFSDsetfillvalue** routine is used to initialize array elements between non-contiguous slab write operations. Setting a fill value places the same value in every array location before the first slab is written. Any hole created by non-contiguous writes can then be recognized by identifying the known fill value. The fill value must have the same number type as the values in the data set. For more information on fill values refer to Section 11.7.1.2 on page 287.

To write a slab to a new data set, the calling program must include the following routine calls:

```

C:          status = DFSDsetdims(rank, dimsizes);
           status = DFSDsetNT(num_type);
           status = DFSDstartslab(filename);
           status = DFSDwriteslab(start, stride, count, data);
           status = DFSDendslab( );

FORTRAN:    status = dssnt(num_type)
           status = dssdims(rank, dim_sizes)
           status = dssslab(filename)
           status = dswwslab(start, stride, edge, data)
           status = dseslab( )

```

When writing slabs to an existing data set, it is impossible to change the number type, array boundaries, fill value, or calibration information. Consequently **DFSDsetNT**, **DFSDsetdims**, **DFSDsetcal**, and **DFSDsetfillvalue** will generate errors if called for an existing data set.

To write a slab to an existing data set, your program should include the following calls:

```

C:          status = DFSDwriteref(filename, ref);
           status = DFSDstartslab(filename);
           status = DFSDwriteslab(start, stride, count, data);
           status = DFSDendslab( );

FORTRAN:    status = dswref(filename, ref)

```

```

status = dssslab(filename)
status = dswwslab(start, stride, edge, data)
status = dseslab( )

```

Because **DFSDwriteslab** offers no overwrite protection, the calling program is responsible for eliminating overlap when arranging slabs within the newly defined data set.

DFSDwriteslab has four arguments: *start*, *stride*, *edge*, and *data*. The arguments *start*, *stride*, and *edge* are defined as they are in the corresponding SD routines.

The DFSD SDS model does not support strides. Pass the *start* array as the *stride* parameter as a place holder. Whatever is passed as the *stride* parameter will be ignored by the DFSD interface.

Although **DFSDendslab** need only be called once per file, it is required to write data to the file. It will also write any attributes defined immediately before the data set is created.

TABLE 11J

DFSDwriteslab Parameter List

Routine Name (Fortran-77)	Parameter	Data Type		Description
		C	Fortran-77	
DFSDwriteslab (sdwwslab)	start	int32 *	integer (*)	Array containing the starting coordinate the write.
	stride	int32 *	integer (*)	Ignored parameter.
	count	int32 *	integer (*)	Array defining the boundaries of the slab.
	data	VOIDP	<valid numeric data type>	Buffer for the data to be written.

11.6.3 Reading Slabs: DFSDreadslab

The programming model for reading one or more slabs involves the following steps:

1. Select an existing SDS.
2. Read the data set using three specialized slab routines.

In addition to reading single slabs of data, **DFSDreadslab** can perform the following sequential access operations:

- Read multiple slabs from the first data set in a file when called repeatedly.
- Read multiple slabs from a specified data set when repeatedly called after **DFSDreadref**.
- Read multiple slabs from sequential data sets when repeatedly called between calls to **DFS-Dgetdims**.

To read a slab, the calling program must include the following routine calls:

```

C:          status = DFSDreadref(filename, ref);
            status = DFSDstartslab(filename);
            status = DFSDreadslab(start, stride, edge, data);
            status = DFSDendslab( );

FORTRAN:    status = dsrref(filename, ref)
            status = dssslab(filename)
            status = dsrslab(start, stride, edge, data)
            status = dseslab( )

```

In addition to **DFSDreadref**, **DFSDgetdims** may also be used to position the read pointer to the appropriate data set. When **DFSDreadslab** is used to read slabs, the coordinates of the *start* array must begin at 0 for each dimension (*start*={0,0, ... 0}) and the size of each dimension

must equal the size of the array itself (`edge={dim_size_1, dim_size_2, dim_size_n}`). As with **DFSDwritelab**, whatever is passed in as the `stride` parameter is ignored. Finally, the data buffer must allocate enough space to hold the data: excess data is truncated.

All parameters of the **DFSDreadslab** routine assume Fortran-77-style one-based arrays - the starting coordinates of the slab must be given as an offset from the origin of the data set where the origin is defined as (`dim 1 = 1, dim 2 = 1, . . . dim n-1 = 1, dim n = 1`). The first element of the slab will be the coordinates specified by the contents of the `start` array. **DFSDreadslab** will extract elements in increasing order until the until the dimensional offset specified by the contents of the `edge` array are encountered.

TABLE 11K

DFSDreadslab Parameter List

Routine Name (Fortran-77)	Parameter	Data Type		Description
		C	Fortran-77	
DFSDreadslab (dswslab)	<code>filename</code>	<code>char *</code>	<code>character* (*)</code>	Name of the HDF file.
	<code>start</code>	<code>int32 *</code>	<code>integer (*)</code>	Array containing the coordinates for start of the slab.
	<code>slab_size</code>	<code>int32</code>	<code>integer (*)</code>	Array of rank containing the size of each dimension of the slab.
	<code>stride</code>	<code>int32 *</code>	<code>integer (*)</code>	Place holder array.
	<code>buffer</code>	<code>VOIDP</code>	<code><valid numeric data type></code>	Array the will used to store the extracted slab.
	<code>buffer_size</code>	<code>int32 *</code>	<code>integer (*)</code>	Array containing the dimensions of the <code>buffer</code> parameter.

11.7 Predefined Attributes and the DFSD Interface

Although they often contain important information, attributes are optional to the data set array and the dimension record. Although both types of attributes use similar names, they are read and written using different sets of routines. All attributes are predefined by the DFSD library.

11.7.1 Writing Data Set Attributes

Data set attributes are described in Chapter 3, titled *Scientific Data Sets (SD API)*. There is a limit of one string attribute per data set.

11.7.1.1 Assigning String Attributes to an SDS: DFSDsetlengths and DFSDsetdatastrs

The DFSD interface provides two function calls for creating data set string attributes: **DFSDsetlengths** and **DFSDsetdatastrs**. **DFSDsetlengths** overrides the default string length and **DFSDsetdatastrs** writes the string. **DFSDsetlengths** and **DFSDsetdatastrs** are optional and may be called individually, or in any order as long as they precede calls to **DFSDadddata** or **DFSDputdata**.

Predefined string attributes are defined as follows:

- *Coordinate system attributes* specify the coordinate system used to generate the original data.
- *Format attributes* specify the format to use when displaying values for the data.
- *Label attributes* contains data array names.
- *Unit attributes* identifies the units of measurement associated with the data.

To assign a predefined attribute to an HDF file, the program must contain the following routine calls:

```
C:          status = DFSDsetlengths(label_len, unit_len, format_len,
                                coords_len);
          status = DFSDsetdatastrs(label, unit, format, coordsys);
          status = DFSDadddata(filename, rank, dimsizes, data);

FORTRAN:    status = dsslens(label_len, unit_len, format_len,
                                coords_len)
          status = dssdast(label, unit, format, coordsys)
          status = dsadata(filename, rank, dimsizes, data)
```

DFSDsetlengths has four arguments: `label_len`, `unit_len`, `format_len`, and `coords_len`. Each parameter reflects the maximum length for the string that will hold the label, unit, format, and coordinate system. Use of **DFSDsetlengths** is optional and usually not necessary.

DFSDsetdatastrs writes null-terminated strings to an HDF file. It has the same four arguments: `label`, `unit`, `format`, and `coordsys`. To avoid the assignment of a string, pass `NULL` as the appropriate argument.

TABLE 11L

DFSDsetlengths and DFSDsetdatastrs Parameter List

Routine Name (Fortran-77)	Parameter	Data Type		Description
		C	Fortran-77	
DFSDsetlengths (dsslens)	<code>label_len</code>	<code>intn</code>	<code>integer</code>	Maximum length for any label string.
	<code>unit_len</code>	<code>intn</code>	<code>integer</code>	Maximum length for any unit string.
	<code>format_len</code>	<code>intn</code>	<code>integer</code>	Maximum length for any format string.
	<code>coords_len</code>	<code>intn</code>	<code>integer</code>	Maximum length for any coordinate system string.
DFSDsetdatastrs (dssdast)	<code>label</code>	<code>char *</code>	<code>character* (*)</code>	Label describing the data.
	<code>unit</code>	<code>char *</code>	<code>character* (*)</code>	Unit to be applied to the data.
	<code>format</code>	<code>char *</code>	<code>character* (*)</code>	Format to be applied in displaying the data.
	<code>coordsys</code>	<code>char*</code>	<code>character* (*)</code>	Coordinate system of the data set.

11.7.1.2 Assigning Value Attributes to a DFSD SDS: **DFSDsetfillvalue**, **DFSDsetrange**, **DFSDsetcal**

The DFSD interface provides the following routines for defining value attributes. All three function calls are optional and may be called in any order provided they precede a call to **DFSDadddata** or **DFSDputdata**.

To assign a value attribute to a data set, the following routines must be called:

```
C:          status = DFSDsetfillvalue(fill_val);
          status = DFSDsetcal(scale, scale_err, offset, offset_err,
                                num_type);
          status = DFSDsetrange(max, min);
          status = DFSDadddata(filename, rank, dimsizes, data);

FORTRAN:    status = dssfill(fill_val)
          status = dsscal(scale, scale_err, offset, offset_err,
                                num_type)
          status = dssrang(max, min)
          status = dsadata(filename, rank, dimsizes, data)
```

DFSDsetrange sets a new range attribute for the current DFSD SDS. **DFSDsetrange** has two arguments: `max` and `min`. The HDF library will not check or update the range attributes as new

data are added to the file, therefore `max` and `min` will always reflect the values supplied by the last **DFSDsetrange** call. The parameters for **DFSDsetrange** is defined in Table 11K below.

DFSDsetfillvalue specifies a new value to the default fill value attribute for an SDS array. It's only argument is `fill_val`, which specifies the new fill value. The fill value must be of the same number type as the array it's written to. To avoid conversion errors, use data-specific fill values instead of special architecture-specific values, such as infinity or Not-a-Number (or *NaN*). Setting the fill value after data is written to the SDS will not update the fill values already written to the data set - it will only change the attribute.

The parameters for **DFSDsetfillvalue** are further defined in Table 11K below.

The **DFSDsetcal** routine creates a calibration record for a specified array and by doing so adds five attributes to the current data set. As the HDF library does not specifically apply calibration information to the data, **SDsetcal** can be called anytime before or after the data is written. **DFSDsetcal** has five arguments; `scale`, `scale_error`, `offset`, `off_err`, and `num_type`. The arguments `scale` and `offset` are defined as they are for the multifile SD API routines.

In addition to the `scale` and `offset`, **DFSDsetcal** also includes both a scale and offset error. The argument `scale_err` contains the potential error of the calibrated data due to scaling and `offset_err` contains the potential error for the calibrated data due to the offset. The `num_type` parameter specifies the number type of the uncalibrated data.

The parameters of **DFSDsetcal** are defined in the following table.

TABLE 11M

DFSDsetfillvalue, DFSDsetrange and DFSDsetcal Parameter List

Routine Name (Fortran-77)	Parameter	Data Type		Description
		C	Fortran-77	
DFSDsetfillvalue (dssfill)	label	char *	character* (*)	Label describing the data.
	unit	char *	character* (*)	Unit to be applied to the data.
	format	char *	character* (*)	Format to be applied in displaying the data.
	coordsys	char *	character* (*)	Coordinate system of the data set.
DFSDsetrange (dssrang)	max	VOIDP	<valid numeric data type>	Highest value in the selected range of data.
	min	VOIDP	<valid numeric data type>	Lowest value in the selected range of data.
DFSDsetcal (dsscal)	cal	float64	real*8	Calibration scale.
	cal_error	float64	real*8	Calibration scale error.
	off	float64	real*8	Uncalibrated offset.
	off_err	float64	real*8	Uncalibrated offset error.
	num_type	int32	integer	Number type of uncalibrated data.

EXAMPLE 3.

Assigning Predefined String Attributes to a File

The following examples demonstrate the steps necessary to assign predefined string attributes to the data set and stores the data set in the file "Example1.hdf". They create a string attribute using **DFSDsetdatastrs** and a value attribute using **DFSDsetrange**. It also demonstrates the use of **DFSDsetlengths** in altering the maximum string length from 255 characters to 50. It then writes the SDS array by calling **DFSDadddata**.

```

C:      #include "hdf.h"

/*
 * Write an array of floating point values representing
 * pressure in a 3x2x5 array.
 */

main( )
{

    float32 data[3][2][5];
    int32 dimsizes[3];
    float32 max, min;
    intn status, rank;
    int i, j, k;

    /* Set the rank and dimension sizes. */
    rank = 3;
    dimsizes[0] = 3;
    dimsizes[1] = 2;
    dimsizes[2] = 5;

    /* Set the dimensions, to define the beginning of a data set. */
    status = DFSDsetdims(rank, dimsizes);

    /* Set the maximum string length to 50. */
    status = DFSDsetlengths(50, 50, 50, 50);

    /* Define the attribute strings and values. */
    status = DFSDsetdatastrs("Pressure Data", "Millibars", "F5.5",
        "None");

    max = 1500.0;
    min = 0.0;
    retn = DFSDsetrange(&max, &min);

    /* Set the rank to 3. */
    rank = 3;

    /* Calculate the data values. */
    for (i = 0; i < 3; i++)
        for (j = 0; j < 2; j++)
            for (k = 0; k < 5; k++)
                data[i][j][k] = i*100.0 + j*10.0 + k;

    /* Write the data set and its attributes to file. */
    status = DFSDadddata("Example3.hdf", rank, dimsizes, data);

}

```

```

FORTRAN:      PROGRAM SET ATTRIBS

                real*8 data(5, 2, 3), max, min, i, j, k
                integer*4 dimsizes(3)
                integer status, rank

                integer dsslens, dssdast, dssrang, dsadata
                integer dssdims

                character*13 label /"Pressure Data"/

```

```
character*9 unit /"Millibars"/
character*4 format /"F5.5"/
character*4 coordsys /"None"/

C      Set the dimensions, to define the data set.
      rank = 3
      dimsizes(1) = 5
      dimsizes(2) = 2
      dimsizes(3) = 3
      status = dssdims(rank, dimsizes)

C      Set the maximum string lengths to 50.
      status = dsslens(50, 50, 50, 50)

C      Define the attribute strings and values.
      status = dssdast(label, unit, format, coordsys)
      max = 1500.0
      min = 0.0
      status = dssrang(max, min)

C      Fill the data array with values.
      do 30 k = 1, 3
        do 20 j = 1, 2
          do 10 i = 1, 5
            data(i, j, k) = i*100.0 + j*10.0 + k
10          continue
20        continue
30      continue

C      Write the data set and its attributes to file.
      status = dsadata("Example3.hdf", rank, dimsizes, data)

      end
```

11.7.2 Reading DFSD Data Set Attributes

The DFSD interface provides two function calls for reading predefined data set attribute strings.

11.7.2.1 Reading Data Set Attributes: DFSDgetdatalen and DFSDgetdatastrs

DFSDgetdatalen returns the length of each string in the attribute. It is useful for determining the length of an attribute before reading it. **DFSDgetdatastrs** reads the label, unit, format, and coordinate system strings.

Attribute data is not read by **DFSDgetdatastrs** until the appropriate routine is called to read the array and its dimension record. If **DFSDgetdatastrs** and **DFSDgetrange** are not called, the array and its dimension record can be read without reading its associated data set attributes. It is also possible to read string and value attributes individually. As attribute data is not actually read by **DFSDgetdatastrs** or **DFSDgetrange**, these calls must be made before calling **DFSDgetdata**.

Reading the attributes of a data set involves the following steps:

1. Determine the length of each attribute string.
2. Read the attribute strings.
3. Read the maximum and minimum values.
4. Read the remainder of the data set.

To assign a predefined attribute to an HDF file, the following routines should be called:

```

C:          status = DFSDgetdatalen(label_len, unit_len, format_len,
                                coords_len);
          status = DFSDgetdatastrs(label, unit, format, coordsys);
          status = DFSDgetrange(max, min);
          status = DFSDgetdata(filename, rank, dimsizes, data);

FORTRAN:    status = dsgdghaln(label_len, unit_len, format_len,
                                coords_len)
          status = dsgdast(label, unit, format, coordsys)
          status = dsgrang(max, min)
          status = dsgdata(filename, rank, dimsizes, data)

```

The parameters of **DFSDgetdatalen** and **DFSDgetdatastrs** are described in the following table.

TABLE 11N

DFSDgetdatalen and DFSDgetdatastrs Parameter List

Routine Name (Fortran-77)	Parameter	Data Type		Description
		C	Fortran-77	
DFSDgetdatalen (dsgdaln)	label_len	intn *	integer	Length of any label string.
	unit_len	intn *	integer	Length of any unit string.
	format_len	intn *	integer	Length of any format string.
	coords_len	intn *	integer	Length of any coordinate system string.
DFSDgetdatastrs (dsgdast)	label	char *	character* (*)	Label describing the data.
	unit	char *	character* (*)	Unit applied to the data.
	format	char *	character* (*)	Format applied to the data.
	coordsys	char *	character* (*)	Coordinate system of the data set.

EXAMPLE 4.

Reading a Data Set and its Attribute Record

These examples read the pressure data set and the dimension attribute record stored in the "Example1.hdf" file into the arrays pointed to by the data, datalabel, dataunit, datafmt and coordsys pointer variables. It assumes the dimension sizes and rank are correct and data strings are less than 10 characters long, with one additional character for the null termination.

```

C:  #include "hdf.h"

main( )
{
    intn rank, maxrank, status;
    int32 dimsizes[3];
    char datalabel[50], dataunit[50], datafmt[50], coordsys[50];
    float64 data[3][2][5];

    maxrank = 3;
    status = DFSDgetdims("Example3.hdf", &rank, dimsizes, maxrank);
    status = DFSDgetdatastrs(datalabel, dataunit, datafmt,
                             coordsys);
    status = DFSDgetdata("Example3.hdf", rank, dimsizes, data);
}

```

```

FORTRAN:    PROGRAM READ SD INFO

            integer dsgdata, dsgdast, dsgdims

```

```
integer*4 dimsizes(3)
integer status, rank, maxrank
character*50 datalabel, dataunit, datafmt
character*10 coordsys
real*8 data(3, 2, 5)

maxrank = 3
status = dsdims('Example3.hdf', rank, dimsizes, maxrank)
status = dsdast(datalabel, dataunit, datafmt, coordsys)
status = dsdata('Example3.hdf', rank, dimsizes, data)

end
```

11.7.2.2 Reading the Value Attributes of a DFSD Data Set: DFSDgetfillvalue and DFSDgetcal

There are three routines in the DFSD interface that retrieve the fill value, range and calibration information of a data set array: **DFSDgetfillvalue**, **DFSDgetrange** and **DFSDgetcal**.

The syntax of these routines are as follows:

```
C:          status = DFSDgetfillvalue(sds_id, fill_val);
           status = DFSDgetrange(max, min);
           status = DFSDgetcal(cal, cal_err, offset, offset_err,
                               num_type);

FORTRAN:    status = dsgfill(fill_value)
           status = dsgrang(max, min)
           status = dsadata(cal, cal_err, offset, offset_err, num_type)
```

DFSDgetfillvalue has two arguments; `sds_id` and `fill_val`. The `sds_id` is the data set identifier and `fill_val` is the space allocated to store the fill value.

The maximum range of values in the data set isn't automatically stored with the data set data; it is explicitly stored through a call to **DFSDgetrange**. The defined range of values can be less than the actual range of values stored in the data set. The value of the `max` parameter is the maximum value of the defined range and the value of the `min` parameter is the minimum value. These values must be of the same number type as the values stored in the data array. In C, the `max` and `min` parameters are indirect pointers specifying the range values, while in Fortran-77 they are variables set to the range values.

DFSDgetcal reads the calibration record of the current data set, if one exists. Each of the parameters of **DFSDgetcal** correspond to the five elements of the calibration record; - four 64-bit floating-point integers followed by a 32-bit integer. The `cal`, `offset`, `offset_err` and `cal_err` parameters are defined as they are in the multifile SD API. This calibration record exists for information only.

The parameters for **DFSDgetfillvalue**, **DFSDgetcal** and **DFSDgetrange** are defined in the following table.

TABLE 11O

Routine Name (Fortran-77)	Parameter	Data Type		Description
		C	Fortran-77	
DFSDgetfillvalue (dsghill)	sds_id	int32	integer	Data set identifier.
	fill_val	VOIDP	<valid numeric data type>	Buffer for the fill value.

DFSDgetcal (dsgcal)	cal	float64 *	real*8	Calibration factor.
	cal_err	float64 *	real*8	Calibration error.
	offset	float64 *	real*8	Uncalibrated offset.
	offset_err	float64 *	real*8	Uncalibrated offset error.
	num_type	int32 *	integer	Type of the uncalibrated data.
DFSDgetrange (dsgrang)	max	VOIDP	<valid numeric data type>	Highest value of the selected range.
	min	VOIDP	<valid numeric data type>	Lowest value of the selected range.

11.7.3 Writing the Dimension Attributes of a DFSD SDS

Dimension attributes are described in Chapter 3, titled *Scientific Data Sets (SD API)*.

11.7.3.1 Writing the String Attributes of a Dimension: DFSDsetlengths and DFSDsetdimstrs

The DFSD interface provides two routines for creating dimension string attributes: **DFSDsetlengths** and **DFSDsetdimstrs**. **DFSDsetlengths** overwrites the default string length and **DFSDsetdimstrs** defines the string text. **DFSDsetdatalengths** and **DFSDsetdimstrs** are optional and must precede calls to **DFSDadddata** or **DFSDputdata**.

Predefined dimension string attributes are limited to one per dimension and contain the following:

- *Format attributes* specify the format to use when displaying values for the dimension.
- *Label attributes* contain dimension names.
- *Unit attributes* identify the unit of measurement associated with the dimension.

To assign a predefined attribute to a dimension, the following routines should be called:

```

C:
    status = DFSDsetlengths(label_len, unit_len, format_len,
                           coords_len);
    status = DFSDsetdimstrs(label, unit, format);
    status = DFSDadddata(filename, rank, dimsizes, data);

FORTRAN:
    status = dsslens(label_len, unit_len, format_len,
                   coords_len)
    status = dssdist(label, unit, format)
    status = dsadata(filename, rank, dimsizes, data)

```

DFSDsetlengths has four arguments: `label_len`, `unit_len`, `format_len`, and `coords_len`. Each parameter specifies the maximum length of the string that defines the label, unit, format, and coordinate system. As mentioned earlier in this chapter, attribute lengths seldom need to be reset..

DFSDsetdimstrs also has four arguments; `dim`, `label`, `unit`, and `format`. The parameter `dim` = 1 for the first dimension, `dim` = 2 for the second dimension, etc.. To avoid assigning a string to the coordinate length, pass `NULL` in the appropriate parameter. **DFSDsetdimstrs** writes null-terminated strings to a file.

The parameters for **DFSDsetlengths** and **DFSDsetdimstrs** are further defined in the following table.

TABLE 11P

DFSDsetlengths and DFSDsetdimstrs Parameter List

Routine Name (Fortran-77)	Parameter	Data Type		Description
		C	Fortran-77	

DFSDsetlengths (dsslen)	label_len	intn	integer	Maximum length of any label string.
	unit_len	intn	integer	Maximum length of any unit string.
	format_len	intn	integer	Maximum length of any format string.
	coords_len	intn	integer	Maximum length of any coordinate system string.
DFSDsetdimstrs (dssdist)	dim	intn	integer	Dimension of the attribute strings.specified by the remaining three parameters
	label	char *	character* (*)	Label describing the data.
	unit	char *	character* (*)	Unit to be applied to the data.
	format	char *	character* (*)	Format to be applied in displaying the data.

11.7.3.2 Writing a Dimension Scale of a DFSD SDS: DFSDsetdimscale

The syntax of the two routines needed to write a dimension scale is the following:

```

C:          status = DFSDsetdimscale(dim, dimsize, scale);
           status = DFSDadddata(filename, rank, dimsizes, data);

FORTRAN:    status = dssdisc(dim, dimsize, scale)
           status = dsadata(filename, rank, dimsizes, data)

```

DFSDsetdimscale has three arguments; *dim*, *dimsize*, and *scale*. These arguments identify the dimension, specify its size, and assign a value to each of its grid points. The parameter *dim* = 1 for the first dimension, and *dim* = 2 for the second dimension. The *dimsize* argument must contain a value equal to the dimension it describes in order for the scale to be applied correctly.

The parameters of **DFSDsetdiscale** are further described in the following table.

TABLE 11Q

DFSDsetdimscale Parameter List

Routine Name (Fortran-77)	Parameter	Data Type		Description
		C	Fortran-77	
DFSDsetdimscale (dssdisc)	dim	intn	integer	Dimension of the current scale.
	dim_size	int32	integer	Size of the current scale.
	scale	VOIDP	<valid numeric data type>	Values of the current scale.

11.7.4 Reading the Dimension Attributes of a DFSD SDS

The DFSD interface provides three routines for reading dimension attributes: **DFSDgetdimlen**, **DFSDgetdimstrs** and **DFSDgetdimscale**. **DFSDgetdimlen** returns the string length for each string in the attribute record. It is a useful routine to call before reading an attribute. **DFSDgetdimstrs** and **DFSDgetdimscale** are used as instructions for reading the dimension attributes. **DFSDgetdimstrs** reads the dimension strings and **DFSDgetdimscale** reads the dimension scale. By avoiding calls to **DFSDgetdimstrs** and **DFSDgetdimscale**, it is possible to read an array and its dimension record without reading the data set attributes associated with it. It is also possible to omit one function call in order to read one attribute without the other. **DFSDgetdimstrs** and **DFSDgetdimscale** must be called before **DFSDgetdata**.

Reading data set attributes involves the following steps:

1. Determine the length of each attribute string.
2. Read the attribute strings.
3. Read the scale values.
4. Read the remainder of the data set.

To assign a predefined attribute to an HDF file, the following routines must be called:

C:

```
status = DFSDgetdimlen(label_len, unit_len, format_len,
                      coords_len);
status = DFSDgetdimstrs(label, unit, format);
status = DFSDgetdimscale(dim, dim_size, scale);
status = DFSDgetdata(filename, rank, dimsizes, data);
```

FORTRAN:

```
status = dsgdiln(label_len, unit_len, format_len,
                coords_len)
status = dsgdist(label, unit, format)
status = dsgdisc(dim, dim_size, scale)
status = dsgdata(filename, rank, dimsizes, data)
```

The parameters for **DFSDgetdimlen**, **DFSDgetdimstrs** and **DFSDgetdimscale** are described in the following table.

TABLE 11R

DFSDgetdimlen, DFSDgetdimstrs and DFSDgetdimscale Parameter List

Routine Name (Fortran-77)	Parameter	Data Type		Description
		C	Fortran-77	
DFSDgetdimlen (dsgdiln)	dim	intn	integer	Dimension of the string attributes describe.
	label_len	intn *	integer	Length of the label attribute string.
	unit_len	intn *	integer	Length of the unit attribute string.
	format_len	intn *	integer	Length of the format attribute string.
DFSDgetdimstrs (dsgdist)	dim	intn	integer	Dimension the string attributes describe.
	label	char *	character* (*)	Label of the dimension.
	unit	char *	character* (*)	Unit to be applied to this dimension.
	format	char *	character* (*)	Format to be applied when displaying the scale.
DFSDgetdimscale (dsgdisc)	dim	intn	integer	Dimension the current scale is attached to
	dim_size	int32	integer	Size of the current scale.
	scale	VOIDP	<valid numeric data type>	Values of the current scale.

