

DFANaddfds/daafds

```
intn DFANaddfds(int32 file_id, char *description, int32 desc_len)
```

<i>file_id</i>	IN:	File identifier returned by Hopen
<i>description</i>	IN:	Sequence of ASCII characters (may include NULL or '\0')
<i>desc_len</i>	IN:	Length of the description

Purpose Adds a file description to a file.

Return value Returns **SUCCEED** (or 0) if successful and **FAIL** (or -1) otherwise.

Description These annotations are associated with the file, not with any particular object within the file. The parameter description can contain any sequence of ASCII characters. It does not have to be a string. Use the general purpose routines **Hopen** and **Hclose** to manage file access as the file annotation routines will not open and close HDF files.

FORTRAN	<pre>integer function daafds(<i>file_id</i>, <i>description</i>, <i>desc_len</i>) integer <i>file_id</i>, <i>desc_len</i> character(*) <i>description</i></pre>
---------	---

DFANaddfid/daafid

intn DFANaddfid(int32 *file_id*, char **label*)

<i>file_id</i>	IN:	The file identifier returned by Hopen .
<i>label</i>	IN:	A null-terminated string.

Purpose Writes a file label to a file.

Return value Returns **SUCCEED** (or 0) if successful and **FAIL** (or -1) otherwise.

Description These annotations are associated with the file, not with any particular object within the file. The label must be a single string. Use the general purpose routines **Hopen** and **Hclose** to manage file access because the file annotation routines will not open and close HDF files for you.

In the FORTRAN-77 version, the string length for the label should be close to the actual expected string length, because in FORTRAN-77 string lengths generally are assumed to be the declared length of the array that holds the string.

FORTRAN integer function daafid(*file_id*, *label*)

```
integer file_id  
character(*) label
```

DFANclear/daclear

```
intn DFANclear( )
```

Purpose Resets all internal library structures and parameters of the DFAN annotation interface.

Return value Returns `SUCCEED` (or 0) if successful and `FAIL` (or -1) otherwise.

Description When a file is regenerated in a single run by a library routine of another interface (such as **DFSDputdata**), **DFANclear** should be called to reset the interface.

FORTRAN `integer function daclear()`

DFANgetdesc/dagdesc

intn DFANgetdesc(char *filename, uint16 tag, uint16 ref, char *desc_buf, int32 buf_len)

<i>filename</i>	IN:	Name of the file
<i>tag</i>	IN:	Tag of the data object assigned the description
<i>ref</i>	IN:	Reference number of the data object assigned the description
<i>desc_buf</i>	OUT:	Buffer allocated to hold the description
<i>buf_len</i>	IN:	Size of the buffer allocated to hold the description

Purpose Reads the description assigned to the data object with the given tag and reference number.

Return value Returns SUCCEED (or 0) if successful and FAIL (or -1) otherwise.

Description The parameter *buf_len* specifies the storage space available for the description. The length of *buf_len* must account for the null termination character appended to the description.

FORTRAN integer function dagdesc(filename, tag, ref, desc_buf, buf_len)

```
character*(*) filename, desc_buf  
integer tag, ref  
integer buf_len
```

DFANgetdesclen/dagdlen

```
int32 DFANgetdesclen(char *filename, uint16 tag, uint16 ref)
```

<i>filename</i>	IN:	Name of the file
<i>tag</i>	IN:	Tag of the data object assigned the description
<i>ref</i>	IN:	Reference number of the data object assigned the description

Purpose Retrieves the length of a description of the data object with the given tag and reference number.

Return value Returns the length of a description if successful and FAIL (or -1) otherwise.

Description This routine should be used to insure that there is enough space allocated for a description before actually reading it.

FORTRAN

```
integer function dagdlen(filename, tag, ref)
```

```
character(*) filename  
integer tag, ref
```

DFANgetfds/dagfds

int32 DFANgetfds(int32 *file_id*, char **desc_buf*, int32 *buf_len*, intn *isfirst*)

<i>file_id</i>	IN:	File identifier returned by Hopen
<i>desc_buf</i>	OUT:	The buffer allocated to hold the description
<i>buf_len</i>	IN:	Size of the buffer allocated to hold the description
<i>isfirst</i>	IN:	Determines the description to be retrieved

Purpose Reads the next file description.

Return value Returns the length of the file description if successful and **FAIL** (or -1) otherwise.

Description If *isfirst* is 0, **DFANgetfds** gets the next file description from an HDF file. For example, if there are three file descriptions in a file, three successive calls to **DFANgetfds** will get all three descriptions. If *isfirst* is 1, **DFANgetfds** gets the first file description.

Valid values for *isfirst* are: 1 to read the first description and 0 to read the next description.

FORTRAN integer function dagfds(*file_id*, *desc_buf*, *buf_len*, *isfirst*)

```
integer file_id, buf_len, isfirst  
character*(*) desc_buf
```

DFANgetfdslen/dagfdsl

```
int32 DFANgetfdslen(int32 file_id, intn isfirst)
```

<i>file_id</i>	IN: File identifier returned by Hopen
<i>isfirst</i>	IN: Determines the description the retrieved length information applies to

Purpose Returns the length of a file description.

Return value Returns the length of the file description if successful and **FAIL** (or -1) otherwise.

Description When **DFANgetfdslen** is first called for a given file, it returns the length of the first file description. In order to get the lengths of successive file descriptions, you must call **DFANgetfds** between calls to **DFANgetfdslen**. Successive calls to **DFANgetfdslen** without calling **DFANgetfds** between them will return the length of the same file description.

Valid values for *isfirst* are: 1 to read the length of the first description and 0 to read the length of the next description.

FORTRAN

```
integer function dagfdsl(file_id, isfirst)
```

```
integer file_id, isfirst
```

DFANgetfid/dagfid

int32 DFANgetfid(int32 *file_id*, char **desc_buf*, int32 *buf_len*, intn *isfirst*)

<i>file_id</i>	IN:	File identifier returned by Hopen
<i>label_buf</i>	OUT:	The buffer allocated to hold the label
<i>buf_len</i>	IN:	Size of the buffer allocated to hold the label
<i>isfirst</i>	IN:	Determines the file label to be retrieved

Purpose Reads a file label from a file.

Return value Returns the length of the file description if successful and **FAIL** (or -1) otherwise.

Description If *isfirst* is 0, **DFANgetfid** gets the next file label from the file. If *isfirst* is 1, **DFANgetfid** gets the first file label in the file. If *buf_len* is not large enough, the label is truncated to *buf_len*-1 characters in the buffer *label_buf*.

Valid values of *isfirst* are: 1 to read the first label, 0 to read the next label

FORTRAN integer function dagfid(*file_id*, *label_buf*, *buf_len*, *isfirst*)

```
integer file_id, buf_len, isfirst  
character(*) label_buf
```

DFANgetfidlen/dagfidl

int32 DFANgetfidlen(int32 *file_id*, intn *isfirst*)

<i>file_id</i>	IN: File identifier returned by Hopen
<i>isfirst</i>	IN: Determines the file label the retrieved length information applies to

Purpose Returns the length of a file label.

Return value Returns the length of the file label if successful and **FAIL** (or -1) otherwise.

Description When **DFANgetfidlen** is first called for a given file, it returns the length of the first file label. In order to retrieve the lengths of successive file labels, **DFANgetfid** must be called between calls to **DFANgetfidlen**. Otherwise, successive calls to **DFANgetfidlen** will return the length of the same file label.

Valid values of *isfirst* are: 1 to read the first label, and 0 to read the next label.

FORTRAN integer function dagfidl(*file_id*, *isfirst*)

```
integer file_id, isfirst
```

DFANgetlabel/daglab

intn DFANgetlabel(char *filename, uint16 tag, uint16 ref, char *label_buf, int32 buf_len)

<i>filename</i>	IN:	Name of the HDF file
<i>tag</i>	IN:	Tag of the data object assigned the label
<i>ref</i>	IN:	Reference number of the data object assigned the label
<i>label_buf</i>	OUT:	Buffer for the label
<i>buf_len</i>	IN:	Size of the buffer allocated for the label

Purpose Reads the label assigned to the data object identified by the given tag and reference number.

Return value Returns SUCCEED (or 0) if successful and FAIL (or -1) otherwise.

Description The parameter *buf_len* specifies the storage space available for the label. The length of *buf_len* must account for the null termination character appended to the annotation.

FORTRAN integer function daglab(filename, tag, ref, label_buf, buf_len)

```
character*(*) filename, label_buf  
integer tag, ref, buf_len
```

DFANgetlabelen/dagllen

```
int32 DFANgetlabelen(char *filename, uint16 tag, uint16 ref)
```

<i>filename</i>	IN:	Name of the file
<i>tag</i>	IN:	Tag of the data object assigned the label
<i>ref</i>	IN:	Reference number the data object assigned the label

Purpose Returns the length of a label assigned to the object with a given tag and reference number.

Return value Returns the length of the label if successful and FAIL (or -1) otherwise.

Description This routine should be used to insure that there is enough space allocated for a label before actually reading it.

FORTRAN

```
integer function dagllen(filename, tag, ref)
```

```
character(*) filename  
integer tag, ref
```

DFANlablist/dallist

```
int DFANlablist(char *filename, uint16 tag, unit16 ref_list[], char *label_list, int list_len, intn label_len, intn start_pos)
```

<i>filename</i>	IN:	Name of the file
<i>tag</i>	IN:	Tag to be queried
<i>ref_list</i>	OUT:	Buffer for the returned reference numbers
<i>label_list</i>	OUT:	Buffer for the returned labels
<i>list_len</i>	IN:	Size of the reference number list and the label list
<i>label_len</i>	IN:	Maximum length allowed for a label
<i>start_pos</i>	IN:	Starting position of the search

Purpose Returns a list of all reference numbers and labels (if labels exist) for a given tag.

Return value Returns the number of reference numbers found if successful and FAIL (or -1) otherwise.

Description Entries are returned from the *start_pos* entry up to the *list_len* entry.

The *list_len* determines the number of available entries in the reference number and label lists, *label_len* is the maximum length allowed for a label, and *start_pos* tells which label to start reading for the given tag. (If *start_pos* is 1, for instance, all labels will be read; if *start_pos* is 4, all but the first 3 labels will be read.) The *ref_list* contains a list of reference numbers for all objects with a given tag. The *label_list* contains a corresponding list of labels, if any. If there is no label stored for a given object, the corresponding entry in *label_list* is an empty string.

Taken together, the *ref_list* and *label_list* constitute a directory of all objects and their labels (where they exist) for a given tag. The *label_list* parameter can display all of the labels for a given tag. Or it can be searched to find the reference number of a data object with a certain label. Once the reference number for a given label is found, the corresponding data object can be accessed by invoking other HDF routines. Therefore, this routine provides a mechanism for the direct access to data objects in HDF files.

```
FORTRAN      integer function dallist(filename, tag, ref_list, label_list,
                                         list_len, label_len, start_pos)

                                         character*(*) filename, label_list
                                         integer ref_list(*)
                                         integer list_len, label_len, start_pos
```

DFANlastref/dalref

uint16 DFANlastref()

Purpose Returns the reference number of the annotation last written or read.

Return value Returns the reference number if successful and FAIL (or -1) otherwise.

FORTRAN integer function dalref()

DFANputdesc/dapdesc

```
int DFANputdesc(char *filename, uint16 tag, uint16 ref, char *description, int32 desc_len)
```

<i>filename</i>	IN:	Name of the file
<i>tag</i>	IN:	Tag of the data object to be assigned the description
<i>ref</i>	IN:	Reference number the data object to be assigned the description
<i>description</i>	IN:	Sequence of ASCII characters (may include NULL or '\0')
<i>desc_len</i>	IN:	Length of the description

Purpose Writes a description for the data object with the given tag and reference number.

Return value Returns SUCCEED (or 0) if successful and FAIL (or -1) otherwise.

Description The parameter description can contain any sequence of ASCII characters; it does not have to be a string. If **DFANputdesc** is called more than once for the same tag/reference number pair, only the last description is stored in the file.

```
FORTRAN      integer function dapdesc(filename, tag, ref, description,
                                         desc_len)

                           character*(*) filename, description
                           integer tag, ref, desc_len
```

DFANputlabel/daplab

```
intn DFANputlabel(char *filename, uint16 tag, uint16 ref, char *label)
```

<i>filename</i>	IN:	Name of the file
<i>tag</i>	IN:	Tag of the data object to be assigned the label
<i>ref</i>	IN:	Reference number the data object to be assigned the label
<i>label</i>	IN:	Null-terminated label string

Purpose Assigns a label to the data object with the given tag/reference number pair.

Return value Returns `SUCCEED` (or 0) if successful and `FAIL` (or -1) otherwise.

FORTRAN

```
integer function daplab(filename, tag, ref, label)
```

```
character(*) filename, label
```

```
integer tag, ref
```

